Libsynexens3 SDK instructions

Version	Revised Date	Adapt SDK version	Description	Editor
v1.0	July4,2022	v0.1.2	Initial Version	Wai Kai
v1.1	July5,2022	v0.1.3	Add interface description	Wai Kai
v1.2	July11,2022	v0.1.3	Add ubuntu environment configuration	Wai Kai

Contents

1.	Desci	riptions	1
		lows environment configuration	
	2.1.	Windows environment configuration (vs2017 as example)	2
	2.2.	Ubuntu environment configuration (cmake as example)	4
3.	API I	Reference	6
	3.1.	Global interface	6
	3.2.	SENSOR control interface	18
	3.3.	Algorithm interface	20
	3.4.	Date type	21
4.	Samp	ole code	26
	4.1.	Get depth frame	26
	4.2.	Get align	27


1. Descriptions

This document introduces code interfaces and demo code for users, the SDK adapt for CS series camera.


2. Windows environment configuration

2.1. Windows environment configuration (vs2017 as example)


a. Create VS project.





b. Select the solution and platform corresponding to the SDK library.



c. Configure the header file path and library path of the SDK in the project properties.







d. After the configuration is completed, you can enter.

2.2. Ubuntu environment configuration (cmake as example)

a. Installation Dependencies

```
sudo apt-get install libusb-1.0-0-dev
sudo apt-get install libudev-dev
```

b. Compile CmakeLists.txt, the process requires familiarity with cmake syntax

```
### PROPERTY OF THE PROPERTY O
```

c. Create Compiled Project File


```
THE THE TOTAL SECTION OF THE T
```

d. make


e. Execute the executable file to test the effect

LD_LIBRARY_PATH needs to be configured before executing the program, in order to find the library files that the program depends on, the example has written run.sh script to facilitate program execution.

 $export\ LD_LIBRARY_PATH=\\ \$LD_LIBRARY_PATH:../lib/:../../third-party/ubuntu\\ 18.04_x64/opencv-4.4.0/lib/x64/shared/.../depth$



f. Calling process diagram Currently, only polling mode calls are supported



3. API Reference

3.1. Global interface

3.1.1. get_device_info

Description: Obtain devices information

Grammar:

const device info *get device info(sy3 error &error) const;

Parameters:

Parameters name	Descriptions	Input/Output
error	Function execution status	Output

The return value:

Return value	Description
device_info	Device information

3.1.2. query_device

Descriptions: query device

Grammar:

device *query_device(sy3_error &error) const;

Parameters:

Parameters name	Description	Input/Output
error	Function execution status	Output

The return value:

Return value	Description
device	Device pointer

3.1.3. sy3_create_pipeline

Description: Create routes

Grammar:

pipeline *sy3_create_pipeline (const context *ctx,sy3_error &error);

Parameters:

Parameters name	Description	Input/Output
ctx	Context currently in use	Input
error	Function execution status	Output

The return value:

Return value	Description
pipeline	Pipeline pointer

3.1.4. sy3_create_config

Description: Creates a configuration parameter pointer

Grammar:

config *sy3_create_config(sy3_error &error)

Parameters:

Parameters name	Description	Input/Output
error	Function execution status	Output

The return value:

Return value	Description
config	Configuration parameter pointer

3.1.5. sy3_get_device_info

Description: Get device information

Grammar:

const char* sy3 get device info(const device* device,sy3 camera info info, sy3 error &error);

Parameters:

Parameters name	Description	Input/Output
device	Device pointer	Input
info	Info Enumeration	Input
error	Function execution status	Output

The return value:

Return value	Description
const char*	Corresponding device information string

Note: The call is invalid until the device is found successfully

3.1.6. Basic interface

device::get_sensor

Description: Get the sensor pointer

Grammar:

const sensor *get sensor(sy3 error &error) const;

Parameters:

Parameters	Description	Input/Output
error	Function execution status	Output

The return value:

Return value	Description
sensor *	sensor pointer

3.1.7. device::get_type

Description: Get device type

Grammar:

const sy3_device_type get_type(sy3_error &error) const;

Parameters:

Parameters	Description	Input/Output
error	Function execution status	Output

The return value:

Return value	Description
sy3_device_type *	Device type

3.1.8. device::get_support_stream

Description: Get the list of data streams supported by the device

Grammar:

const std::vector<sy3_stream> get_support_stream(sy3_error &error) const

Parameters:

Parameters name	Description	Input/Output
error	Function execution status	Output

The return value:

Return value	Description
const std::vector <sy3_stream></sy3_stream>	Data flow list

3.1.9. device::get_support_format

Description: Get supported data formats

Grammar:

const std::vector<sy3 format> get support format(sy3 error &error) const;

Parameters:

Parameters name	Description	Input/Output
error	Function execution status	Output

The return value:

Return value	Description
const std::vector <sy3_format></sy3_format>	Data flow list

3.1.10. device::get_support_format

Description: Get the format supported by the specified data stream of the device

Grammar:

const std::vector<sy3_format> get_support_format(sy3_stream stream,sy3_error &error) const;

Parameters:

Parameters name	Description	Input/Output
stream	Data flow type	Input
error	Function execution status	Output

The return value:

Return value	Description
const std::vector <sy3_format></sy3_format>	Data format list

3.1.11. config::enable_stream

Description: Enables the specified data flow

Grammar:

void enable stream(sy3 stream stream, uint16 t width, uint16 t height,sy3 error &error);

Parameters:

Parameters name	Description	Input/Output
stream	Data type to enable	Input
width	Width of data stream image	Input
height	Height of data stream image	Input
error	Function execution status	Output

Return value: None

Note: This function is only called valid before the pipeline is started. It is invalid when called during the pipeline running.

3.1.12. config::disable_stream

Description: Disables the specified data flow

Grammar:

void disable_stream(sy3_stream stream,sy3_error &error);

Parameters:

Parameters name	Description	Input/Output
stream	Type of data flow to disable	Input
error	Function execution status	Output

Return value: None

3.1.13. config::disable_all_streams

Description: Disable all data flows

Grammar:

void disable_all_streams(sy3_error &error);

Parameters:

Parameters name	Description	Input/Output
error	Function execution status	Output

Return value: None

3.1.14. pipeline::start

Description: Start pipeline

Grammar:

void start(const config *cfg,sy3 error &error);

Parameters:

Parameters name	Description	Input/Output
cfg	Pipeline configure	Input
error	Function execution status	Output

Return value: None

3.1.15. pipeline::get_process_engin

Description: Get the algorithm instance pointer

Grammar:

process engine* get process engin(sy3 error &error);

Parameters:

Parameters name	Description	Input/Output
error	Function execution status	Output

The return value:

Return value	Description
process engine*	Algorithm instance pointer

3.1.16. pipeline::stop

Description: stop pipeline

Grammar:

void stop(sy3_error &error);

Parameters:

Parameters name	Description	Input/Output
error	Function execution status	Output

Return value: None

3.1.17. pipeline::wait_for_frames

Description: Get pipeline frame set

Grammar:

frameset *wait for frames(unsigned int timeout ms,sy3 error &error);

Parameters:

Parameters name	Description	Input/Output
timeout_ms	overtime	Input
error	Function execution status	Output

The return value:

Return value	Description
frameset *	Frame gather

3.1.18. pipeline::get_device

Description: Get the current device

Grammar:

const device *get device(sy3 error &error);

Parameters:

Parameters name	Description	Input/Output
error	Function execution status	Output

The return value:

Return value	Description
const device *	Device pointer

3.1.19. frameset::get_depth_frame

Description: Get depth frame

Grammar:

depth_frame *get_depth_frame();

Parameters: none

The return values

depth frame *	Depth frame data pointer
depui_frame	Depui frame data pointer

3.1.20. frameset::get_ir_frame

Description: Get ir frame

Grammar:

ir_frame *get_ir_frame();

Parameters: none
The return values

Return value	Description
ir_frame *	Ir frame data pointer

3.1.21. frameset::get_raw_frame

Description: Get device information

Grammar:

raw frame *get raw frame();

Parameters: none The return value

Return value	Description
raw_frame *	raw frame data pointer

Note: At present, raw_ Frame data is only open to internal calibration, and external users cannot obtain raw data

3.1.22. frame::get_width

Description: Get the width of image

Grammar:

const int get_width();

Parameters: none The return value:

Return value	Description
const int	Width

3.1.23. frame::get_height

Description: Get the height of image

Grammar:

const int get height();

Parameters: none The return value:

Return value	Description
const int	Height

3.1.24. frame::get_type

Description: Get the type of frame

Grammar:

const sy3_stream get_type();

Parameters: none The return value:

Return value	Description
const sy3_stream	Frame type

3.1.25. depth_frame::get_data

Description: Obtain the frame image array, store the data in the form of uint16 type two-dimensional array (uint16 [h] [w]), and return the array pointer to the caller as the return value. The specific data format is as follows:

depth[0][0]	depth[0][1]	 depth[0][width-2]	depth[0][width-1]
depth[1][0]	depth[1][1]	 depth[1][width-2]	depth[1][width-1]
depth[height-1][0]	depth[height-1][1]	 depth[height-1][width-2]	depth[height-1][width-1]

Grammar:

void *get data();

Parameters: none The return value:

Return value	Description
--------------	-------------

void *	Frame data pointer
--------	--------------------

Note: The return value type is void *, and you need to manually convert it to uint16*

3.1.26. depth_frame::apply_colormap

Description: Obtain the data mapped rgb (BGR format), store the data in the form of uint8 type 3D array (uint8 [h] [w] [3]), and return the array pointer to the caller as the return value. The specific data format is as follows:

rgb[0][0][(b)0]	rgb[0][0][(g)1]	rgb[0][0][(r)2]			 rgb[0][w-1][0]	rgb[0][w-1][1]	rgb[0][w-1][2]
rgb[1][0][0]	rgb[1][0][1]	rgb[1][0][2]			 rgb[1][w-1][0]	rgb[1][w-1][1]	rgb[1][w-1][2]
rgb[h-1][0][0]	rgb[h-1][0][1]	rgb[h-1][0][2]			 rgb[h-1][w-1][0]	rgb[h-1][[w-1][1]	rgb[h-1][[w-1][2]

Grammar:

uint8 t *apply colormap();

Parameters: none

The return value:

Return value	Description
uint8 t*	rgb image numeric pointer

3.1.27. frame::get_profile

Description: Get frame configure

Grammar:

const stream_profile *get_profile() const;

Parameters: none

The return values

Return value	Description
const stream profile *	Frame configuration pointer

3.1.28. frame::dump

Description: Save frames locally for debugging

Grammar:

int dump(const char *filenam);

Parameters:

Parameters name	Description	Input/Output
filenam	File name to save	Input

The return value:

Return value	Description
int	execution result

Note: This function will not automatically create folders. If there are folders in the path that have not been created, please create them manually.

3.1.29. points::get_points

Description: Obtain 3D point cloud data, which is stored in the form of float type 3D array float [h] [w] [3]. The array pointer is returned to the caller as a return value. The specific data format is as follows:

points[0][0][(x)0]	points[0][0][(y)1]	points[0][0][(z)2]	 points[0][w-1][0]	points[0][w-1][1]	points[0][w-1][2]
points [1][0][0]	points[1][0][1]	points[1][0][2]	 points[1][w-1][0]	points[1][w-1][1]	points[1][w-1][2]
points [h-1][0][0]	points[h-1][0][1]	points[h-1][0][2]	 points[h-1][w-1][0]	points[h-1][[w-1][1]	points[h-1][[w-1][2]

Grammar:

float *get_points();

Parameters: none

The return value:

Return value	Description
float *	Point cloud array pointer

3.1.30. points::get_length

Description: Get point cloud length

Grammar:

int get length();

Parameters:

Parameters name Description Input/Output
--

error	Function execution status	Output
-------	---------------------------	--------

The return value:

Return value	Description
int	Point cloud length

3.2. SENSOR control interface

3.2.1. sensor::set_option

Description: configure sensor function attribute value

Grammar:

int set_option(sy3_option option, uint16_t value,sy3_error &error);

Parameters:

Parameters name	Description	Input/Output
option	Function Item Enumeration	Input
value	Set value	Input
error	Execution status	Output

The return value:

Return value	Description
int	whether or not success

3.2.2. sensor::set_option

Description: Configure the extreme value of the sensor function item

Grammar:

int set option(sy3 option option, uint16 t max, uint16 t min,sy3 error &error);

Parameters:

Parameters name	Description	Input/Output
option	Function Item Enumeration	Input
max	Max	Input
min	Min	Input
error	Function execution status	Output

The return value:

Return value Description

3.2.3. sensor::get_option

Description: Get the extreme value range of sensor function attribute

Grammar:

int get_option(sy3_option option, uint16_t &max, uint16_t &min,sy3_error &error);

Parameters:

Parameters name	Description	Input/Output
option	Function Item Enumeration	Input
max	Max	Input
min	Min	Input
error	Function execution status	Output

The return value:

Return value	Description
int	whether or not success

3.2.4. sensor::get_option

Description: Get the extreme value of sensor function attribute

Grammar:

int get option(sy3 option option, uint16 t &value,sy3 error &error);

Parameters:

Parameters name	Description	Input/Output
option	Function Item Enumeration	Input
value	Attribute Value	Input
error	Function execution status	Output

The return value:

Return value	Description
int	whether or not success

3.3. Algorithm interface

3.3.1. process_engine::comptute_points

Description: Compute point clouds

Grammar:

points *comptute points(depth frame *depth,sy3 error &error) const;

Parameters:

Parameters name	Description	Input/Output
depth	Depth frame to be converted to	Input
	point cloud	
error	Function execution status	Output

The return value:

Return value	Description
points	Points cloud pointer

Note: The function has applied for memory for the point cloud internally. If the point cloud data is no longer needed, it needs to be released manually, that is, call delete points

3.3.2. process_engine::align_to_rgb

Description: rgbd alignment

Grammar:

sy3::frameset *align to rgb(depth frame *depth,rgb frame *rgb,sy3 error &error);

Parameters:

Parameters name	Description	Input/Output
depth	Depth pointer	Input
rgb	rgb pointer	Input
error	Function execution status	Output

The return values:

Return value	Description
frameset *	Aligned rgb and depth sets

Note: Currently, only mapping from rgb resolution 1920x1080 to depth resolution 640x480 is supported. The align rgb resolution and align depth resolution of the mapping output are 1920x1080 and 1920x1080 respectively.

3.4. Date type

3.4.1. sy3 error

```
enum sy3_error

{

SUCCESS = 0,
INVALID_PID,
INVALID_VID,
DEVICE_NOT_FOUND,
INVALID_FORMAT,
INCONSISTENCY_RES,
OPEN_FAILED,
NOT_IMPLEMENTED,
INVALID_INSTANCE,
}sy3_error;
```

Parameters:

Parameters name

SUCCESS
INVALID_PID
INVALID_VID
DEVICE_NOT_FOUND
INVALID_FORMAT
INCONSISTENCY_RES
OPEN_FAILED
NOT_IMPLEMENTED
INVALID_INSTANCE

3.4.2. sy3_device_type

```
enum sy3_device_type
{
    DEVICE_CS30,
    DEVICE_CS20,
} sy3_device_type;
```

Parameters:

Parameter description
DEVICE_CS30
DEVICE_CS20

3.4.3. sy3_camera_info

```
enum sy3_camera_info

{
    SY3_CAMERA_INFO_NAME,
    SY3_CAMERA_INFO_SERIAL_NUMBER,
    SY3_CAMERA_INFO_FIRMWARE_VERSION,
    SY3_CAMERA_INFO_RECOMMENDED_FIRMWARE_VERSION,
    SY3_CAMERA_INFO_PRODUCT_ID,
    SY3_CAMERA_INFO_COUNT
} sy3_camera_info;
```

Parameters:

Parameters description
SY3_CAMERA_INFO_NAME
SY3_CAMERA_INFO_SERIAL_NUMBER
SY3_CAMERA_INFO_FIRMWARE_VERSION
SY3_CAMERA_INFO_RECOMMENDED_FIRMWARE_VERSION
SY3_CAMERA_INFO_PRODUCT_ID

3.4.4. sy3_stream

```
enum sy3_stream
{
    SY3_STREAM_NONE,
    SY3_STREAM_DEPTH=2,
    SY3_STREAM_RGB,
    SY3_STREAM_IR,
    SY3_STREAM_COUNT,
} sy3_stream;
```

Parameters:

Parameters description
SY3_STREAM_NONE
SY3_STREAM_DEPTH
SY3_STREAM_RGB
SY3_STREAM_IR

3.4.5. sy3_format

```
struct sy3_format {
    sy3_stream stream;
    int width;
    int height;
}sy3_format;
```

Parameters:

Parameters description
stream
width
neight

3.4.6. intrinsics

```
struct sy3_intrinsics{
   int width;
   int height;
   float ppx;
   float ppy;
   float fx;
   float fy;
   float coeffs[5];
} sy3_intrinsics;
```

Parameters:

Parameters description
width
height
ррх
рру
fx
fy
coeffs[5]

3.4.7. sy3_option

```
typedef enum sy3_option {
    SY3_OPTION_EXPOSURE,
    SY3_OPTION_EXPOSURE_RANGE,
    SY3_OPTION_DISTANCE_RANGE,
    SY3_OPTION_DEFAULT_DISTANCE_RANGE,
    SY3_OPTION_RGB_IMAGE_FLIP,
    SY3_OPTION_RGB_IMAGE_MIRROR,
    SY3_OPTION_TOF_IMAGE_FLIP,
    SY3_OPTION_TOF_IMAGE_MIRROR,
    SY3_OPTION_DEPTH_IMAGE_MIRROR,
    SY3_OPTION_DEPTH_IMAGE_FILTER,
    SY3_OPTION_COUNT,
} sy3_option;
```

Description:

Parameters description	Description
SY3_OPTION_EXPOSURE	Exposure time; unit: us
SY3_OPTION_EXPOSURE_RANGE	Exposure time range

SY3_OPTION_DISTANCE_RANGE	Displayed distance range
SY3_OPTION_DEFAULT_DISTANCE_RANGE	Default distance range
SY3_OPTION_RGB_IMAGE_FLIP	Rgb flip
SY3_OPTION_RGB_IMAGE_MIRROR	Rgb mirror
SY3_OPTION_TOF_IMAGE_FLIP	Tof flip
SY3_OPTION_TOF_IMAGE_MIRROR	Tof mirror
SY3_OPTION_DEPTH_IMAGE_MIRROR	depth mirror
SY3_OPTION_DEPTH_IMAGE_FILTER	depth filter

4. Sample code

4.1. Get depth frame

```
//仅截取关键代码,详细代码请参阅 samples 源码
#include "libsynexens3/libsynexens3.h"
int main(int argc, char **argv)
{
    sy3::sy3 error e;
    printf("version:%s \n", sy3::sy3_get_version(e));
    sy3::context *ctx = sy3::sy3_create_context(e);
    sy3::device *dev = ctx->query device(e);
    if (e != sy3::sy3_error::SUCCESS) {
        printf("error:%s \n", sy3::sy3 error to string(e));
        return 0;
    sy3::pipeline *pline = sy3::sy3 create pipeline(ctx, e);
    sy3::config *cfg = sy3_create_config(e);
    cfg->enable_stream(sy3::sy3_stream::SY3_STREAM_DEPTH,640, 480, e);
    pline->start(cfg, e);
    bool quit = false;
    while (!quit)
        sy3::frameset *frameset = pline->wait_for_frames(SY3_DEFAULT_TIMEOUT, e);
        sy3::depth_frame *depth_frame = frameset->get_depth_frame();
        show depth frame (depth frame);
        delete frameset;
        if (cv::waitKey(1) == 'q') {
             pline->stop(e);
             quit = true:
    system("pause");
    return 0;
```

4.2. Get align

```
//仅截取关键代码,详细代码请参阅 samples 源码
#include "libsynexens3/libsynexens3.h"
int main(int argc, char **argv)
    sy3::sy3_error e;
    sy3::context *ctx = sy3::sy3_create_context(e);
    sy3::device *dev = ctx->query_device(e);
    if (e != sy3::sy3 error::SUCCESS) {
         return 0:
    sy3::pipeline *pline = sy3::sy3_create_pipeline(ctx, e);
    sy3::config *cfg = sy3_create_config(e);
    cfg->enable_stream(sy3::sy3_stream::SY3_STREAM_DEPTH, 640, 480, e);
    cfg->enable_stream(sy3::sy3_stream::SY3_STREAM_RGB, 1920, 1080, e);
    pline->start(cfg, e);
    bool quit = false;
    while (!quit)
         switch (cv::waitKey(1)) {
         case 'q': {
             pline->stop(e);quit = true;
         }break;
         case 'e': {
         //设置曝光时间,单位 us
         dev->get sensor(e)->set option(sy3::sy3 option::SY3 OPTION EXPOSURE, 10,
         e);
         }break;
         default: break;
         sy3::frameset *frameset = pline->wait for frames(SY3 DEFAULT TIMEOUT, e);
         sy3::depth_frame *depth_frame = frameset->get_depth_frame();
         sy3::rgb_frame *rgb_frame = frameset->get_rgb_frame();
         sy3::process_engine *engine = pline->get_process_engin(e)
         sy3::frameset *align_set=engine->align_to_rgb(depth_frame, rgb_frame, e);
         show_depth_frame(align_set->get_depth_frame(), "algin_depth");
         show_rgb_rgb_frame(align_set->get_rgb_frame(), "algin_rgb");
         delete frameset;
         delete align_set;
    return 0;}
```